



AN INVITATION TO PROGRAMMING[™] 2:

WRITING PROGRAMS ONE AND TWO



ATARI® A Warner Communications Company

Model CX4106 Use with ATARI® 400[™] or ATARI 800[™] PERSONAL COMPUTER SYSTEMS




AN INVITATION TO PROGRAMMING[™] 2: Writing Programs One and Two



Every effort has been made to ensure that this manual accurately documents this product of the ATARI Computer Division. However, because of the ongoing improvement and update of the computer software and hardware, ATARI, INC. cannot guarantee the accuracy of printed material after the date of publication and cannot accept responsibility for errors or omissions.


Reproduction is forbidden without the specific written permission of ATARI, INC., Sunnyvale, CA 94086. No right to reproduce this document, nor the subject matter thereof, is granted unless by written agreement with, or written permission from the Corporation.

MANUAL AND PROGRAM CONTENTS © 1981 ATARI, INC.



CONTENTS

1	INTRODUCTION	1
2	HOW TO USE THIS COURSE	3
	ATARI Components Required General Instructions for Loading the	3
	Cassette Tape	3
	Preparation for the Practice Sessions	5
3	SUMMARY OF LESSONS:	
	WRITING PROGRAMS ONE	7
4	DESCRIPTION OF FRAMES FOR	
	WRITING PROGRAMS ONE	9
	Lesson One: Keyboard	9
	Lesson Two: Printing on the Television Screen	9
	Lesson Three: Characteristics of a Program Lesson Four: Names and Numbers in Memory	11 15
	Lesson Five: Computer Logic	15
	Lesson Six: Library Function	23
	Lesson Seven: FOR/NEXT Loops	25
	Final Quiz: Writing Programs One	28
5	SUMMARY OF LESSONS:	
	WRITING PROGRAMS TWO	29
6	DESCRIPTION OF FRAMES FOR	
	WRITING PROGRAMS TWO	31
	Lesson One: Screen Formatting Instructions	31
	Lesson Two: READ/DATA	33
	Lesson Three: Arrays Lesson Four: PEEK and POKE	35 38
	Lesson Five: ATASCII Code and Instructions	40
	Lesson Six: String Handling	43
	Lesson Seven: Multiple Statements	46
	Lesson Eight: Subroutines	48
	Final Ouiz: Writing Programs Two	51




INTRODUCTION

AN INVITATION TO PROGRAMMING[™] 2 covers beginning through advanced BASIC programming techniques. This course provides a two-part format with an interactive style of presentation, allowing you to experience immediate use of your computer. Completion of WRITING PROGRAMS ONE supplies you with rudimentary skills which can be applied in extending your knowledge of BASIC through actual "hands-on" application in WRITING PROGRAMS TWO.

The course has the following components:

- Cassette for Writing Programs One containing both the computer program and audio material
- Cassette for Writing Programs Two containing both the computer program and audio material
- This workbook containing both sections of the course to be used as a study guide and reference source



HOW TO USE This course

ATARI Components Required

- ATARI[®] 400TM or ATARI 800TM Personal Computer System with:
- 8K (minimum) Random Access Memory (RAM) ATARI BASIC Computing Language Cartridge
- ATARI 410[™] Program Recorder
- Writing Programs One Program Cassette Writing Programs Two Program Cassette

GENERAL INSTRUCTIONS FOR LOADING THE CASSETTE TAPE

Refer to Figure 1.

- 1. Connect the ATARI 400 or ATARI 800 Personal Computer System to your television set and to a wall outlet as instructed in the Operator's Manual.
- 2. Make sure that the ATARI 410 Program Recorder is properly connected to the computer console and to a wall outlet (see your ATARI 410 Program Recorder Operator's Manual for further details, if necessary).

Note: If you have "daisy chained" (connected in series) other ATARI peripherals to your computer console and do not wish to disconnect them, connect your ATARI 410 Program Recorder to the I/O CONNECTOR of the last unit in the chain.

3. Make sure that at least 8K of RAM is installed in your ATARI Personal Computer System. See the Operator's Manual for Memory Module[™] loading instructions.

Note: If an ATARI Disk Drive is connected to the computer console, the Disk Operating System (DOS) and system software use some of the available Random Access Memory (RAM). The amount of RAM used varies with the version of DOS you are using. Take this overhead into account when calculating the amount of RAM required to run a program.

- Open the cartridge door and insert the ATARI BASIC cartridge into the cartridge slot. Use the LEFT CARTRIDGE slot on the ATARI 800 Personal Computer System. Close the cartridge door.
- 5. Turn on your television set. (You may have to adjust the volume on your television set, since the voice from the audio track comes from the television speaker.)

- 6. Turn on your ATARI Personal Computer System. The POWER switch is on the right side of the computer console.
- 7. If all equipment is properly connected and turned on, your television screen should display the READY prompt, with the white cursor just below.
- 8. Press STOP/EJECT on your Program Recorder to open the cassette door.
- 9. Load Lesson One by holding the cassette tape so that the label (Side 1) is up and the tape leader is facing you.
- 10. Slide the cassette into the cassette holder and close the door.
- 11. If necessary, press **REWIND** to rewind the tape to the beginning. (Set the counter on the Program Recorder to 000.)
- 12. Type **CLOAD** on the computer keyboard and press **RETURN**. The computer will "beep" once to remind you to press **PLAY** on the Program Recorder.
- 13. Press **PLAY** and the **RETURN** key to start the tape. Through the window in the Program Recorder, note that the tape is turning. The beeps and other sounds you hear coming from the television speaker tell you that Lesson One is being loaded into computer memory.

Note: If you have problems loading either of the course programs and you have peripherals in addition to the Program Recorder attached to the computer console, try disconnecting the other peripherals and connecting the Program Recorder directly to the computer console to isolate any problem. If problems persist, consult the ATARI 410 Program Recorder Operator's Manual.

- 14. When the television screen displays the READY prompt, the first program encountered on the cassette, Lesson One, has been loaded into the computer. Make sure that the **PLAY** button on the Program Recorder is still down (and remains down). On the chart provided, make a note of the number on the Program Recorder's counter. Enter this number in the START AUDIO column for Lesson One. If you want to run Lesson One again, simply rewind the tape to this number. As you proceed with the course, similarly keep track of the START AUDIO numbers of the other lessons.
- 15. Type **RUN** and press **RETURN** to start Lesson One. From now on, follow the instructions given in the lesson. At the end of Lesson One, make a note of the Program Recorder counter number. Enter this number in the END AUDIO column for Lesson One.
- DO NOT rewind the cassette tape. When you are ready to begin Lesson Two, follow the same procedure as you did to load Lesson One (begin with Step 12). Follow this procedure for all the lessons in the course and for the Final Quiz.

To go to a specific lesson in the course: Completely **REWIND** the tape. Set the counter at 000. Push **FAST FORWARD** on the Program Recorder. Advance the tape until you reach the START LOADING number that you entered on the chart.

To repeat a lesson just completed: **REWIND** the tape to the START AUDIO number on your chart.




Figure 1 Loading a Cassette Tape

PREPARATION FOR THE PRACTICE SESSIONS

Memory in a computer system is divided into two components, ROM and RAM:

ROM. Read-Only Memory contains programs permanently stored in your computer by the manufacturer. This information is essential for computer operation. The ROM programs are called read-only because they can only be read, and they cannot be altered by use of the keyboard.


RAM. Random Access Memory temporarily stores programs and data in your computer. You can enter information directly into RAM from the keyboard, which allows you to create new programs, or bring stored data into your RAM workspace from diskette, cassette, or cartridge.

Turning off the computer console clears all the information stored in RAM. To write new data without turning your console off and on, use the BASIC instruction, **NEW** followed by **RETURN**. A **NEW** command clears any information in RAM.

A **CLOAD** command brings a stored program from the cassette into RAM. To clear out this program and prepare for the practice sessions, you MUST enter the **NEW** command.

The following statement is repeated at the beginning of each practice session because of its importance:

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.



3

SUMMARY OF LESSONS: WRITING PROGRAMS ONE

Lesson One: Keyboard

Reviews the ATARI computer console keyboard.

Lesson Two: Printing on the Television Screen

Covers the PRINT command for words or math in the direct operating mode. Includes the rules for procedural precedence in evaluating mathematical expressions.

Lesson Three: Characteristics of a Program

Explains BASIC program formatting and simple revisions. Gives initial exposure to the deferred operating mode by explaining a program RUN.

Lesson Four: Names and Numbers in Memory Explains the manipulation of numeric and string variables.

Lesson Five: Computer Logic

Shows how to use IF/THEN and GOTO statements to allow for logical branching in the structure of a program.

Lesson Six: Library Function

Explains intrinsic functions available on the computer to get generation of random numbers, absolute or integer values, as well as square root computation.

Lesson Seven: FOR/NEXT Loops


Covers repetitive action using FOR/NEXT loops, the STEP instruction, and nesting of FOR/NEXT loops.

Final Quiz: Writing Programs One

A comprehensive review of the material covered in the course.

WRITING		CASSETTE RECORDER COUNTER VALUE				
WRITING PROGRAMS ONE	LESSON	START LOADING	START AUDIO	END AUDIO		
SIDE 1	1	000				
	2					
	3					
	4					
SIDE 2	5	000				
	6					
	7					
	FINAL TEST					

Figure 2 Program Recorder Counter Numbers for Lessons in Writing Programs One



4

DESCRIPTION OF FRAMES FOR WRITING PROGRAMS ONE

LESSON ONE: KEYBOARD

The first lesson is a quick review of the ATARI keyboard. It includes an explanation of the following important keys:

- Backspace key (DELETE BACK S)
- Capital letter/lower case key CAPS LOWR
- Quotation mark key
- ATARI symbol key for reverse letters
- Break, control, escape keys (BREAK, CTRL, ESC)
- Math keys (+, -, I, *)

When you are ready, load Lesson Two on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON TWO: F PRINTING ON THE TELEVISION ¹ SCREEN

Frame 1: Summary of Lesson Two

- THE TELEVISION 1. **PRINT** causes a display on the screen of whatever text or numeric characters you have placed within quotes.
 - 2. **PRINT** is always in capital letters. Material you put inside the quotes can be upper or lower case, alpha or numeric characters.
 - 3. **PRINT** used without quotes performs mathematical functions according to the following rules:

The computer performs the math computation by doing:

- Multiplication and division inside parentheses first.
- Addition and subtraction inside parentheses next
- Multiplication and division outside parentheses next
- Addition and subtraction last.

On each step, the computer moves from left to right across the expression.

Example: (4/2+1) * 3 + (2+2) - 12

Step 1: (2+1) * 3 + (2+2) - 12 Step 2: 3 * 3 + 4 - 12 Step 3: 9 + 4 - 12 Step 4: 1

Computer prints: 1

Frame 2: Practice Session for Lesson Two

Note: To clear RAM computer memory, type NEW and press RETURN before EVERY practice session and between each example program.

Enter each line on the computer by typing the command. Press **RETURN** to see the result. Try to determine beforehand what will be displayed on the screen and see if you're right.

PRINT "HELLO" PRINT "MY NAME IS GEORGE" PRINT "OH" PRINT "Oh boy!" print "OOPS" PRINT "OOPS" PRINT "@#\$%&" PRINT "THIS IS RIGHT"

Try this math. Enter each command and press RETURN.

PRINT "3-3" PRINT "7*7" PRINT 4*4 PRINT 10/2+4-5 PRINT (3*6)/(3*3) PRINT 3*6/3*3 PRINT 25+(6/2-2)-8 PRINT 200/(3+2)*2-60 PRINT (6-2)*2*5 Now use the computer to solve these problems:

- Add three numbers and PRINT the result (pick the numbers).
- Compute the average of five numbers. (Add them and divide by 5. Remember the operational precedence of mathematical expressions when you enter this exercise into the computer. Placement of parentheses is emphasized in this case.)

When you are ready, load Lesson Three on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON THREE: CHARACTERIS-TICS OF A PROGRAM


Frame 3: Entering a Program




Frame 4: Example of Executing Consecutive Line Numbers




Frame 5: Insertion of Program Line




Frame 6: Deletion of Program Line



Frame 7: Use of END Command



Frame 8: Use of STOP Command




Frame 9: Summary of Lesson Three


- 1. A program is a series of logical steps for the computer. Each step gets a unique line number.
- 2. RUN tells the computer to execute the lines in consecutive numerical order.
- 3. **LIST** tells the computer to display all the program lines in consecutive numerical order.
- 4. **NEW** erases the program from computer memory.
- 5. **END** or **STOP** statements cause the computer to terminate program execution at the line number of the command.
- 6. To edit your program
 - Retype the line.
 - Add a new line with a line number that is numerically between other lines (25 placed between line numbers 20 and 30), or
 - Remove a line by typing its number and pressing RETURN.

Frame 10: Practice Session for Lesson Three

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.


Enter and run each of these programs.





COMPUTER IS THE ATARI"

Use the core program above. Add the following additional program lines one at a time to the basic program. After you add each line, run the program to see the effect of the change.




When you are ready, load Lesson Four on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **BETURN** to start the lesson.


LESSON FOUR: Frame 11 NAMES AND NUMBERS IN MEMORY

READY 10 PRIN1 20 LET E 30 LET L 50 LET S 60 PRIN1 70 PRIN1 80 LET S 90 PRIN1	BIGDIPPER=7 ITTLE=7 OGSTAR=1 STARS=BIGDIPPE STARS TARS=STARS+1	COUNT STARS" R+LITTLE+DOGS ING STAR!"	TAR











Frame 14



Frame 15



Frame 16: Summary of Lesson Four

1. Variables identify memory locations in which the computer stores specific alpha or numeric characters, for example, the result of a computation or an assigned value.

- 2. Variable types determine the kind of labels required.
 - Numeric variables reference numbers ONLY.
 - String variables store any assigned sequence of alpha or numeric characters or their combination.

Each item of information is given a name, which will be used throughout the program to refer to that particular item. This name is called an identifier.

- 3. Specific rules for variable labels include:
 - Assign identifiers like A, B, C3, DE49 to numeric variables.
 - Assign identifiers like A\$, B2\$, ERROR\$ to string variables.
 - DO NOT use reserved BASIC words as labels, such as: FOR, NEXT, DIM, LET, PRINT.
- 4. Commands for variable operation include:
 - LET stores numbers or letters into a variable.
 - LET X = 100
 - LET X\$ = "SHIRLEY"
 - DIM signifies a maximum amount of characters allowed into a variable. DIM A\$(10)
 - **INPUT** commands the computer to wait for entry of the number or word to be stored in the numeric or string variable.

INPUT X INPUT X\$ (remember to DIM X\$ first)

Frame 17: Practice Session for Lesson Four

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

Run each of these sample programs.

READY 10 PRINT "PROGRAM TO BE" 20 LET SIDE=5 30 LET VOL=SIDE*SIDE* 40 PRINT VOL 50 END	FIND VOLUME OF	GU
40 PRINT VOL 50 END	*	

Add these lines to make an expanded program.


32 PRINT "SIDE =";

34 PRINT SIDE

36 PRINT "VOLUME =";

THEN change Line 20 to find the volume of other cubes.

The following program converts centimeters to inches.




Now change Line 10 and run the program several times, typing in a different number each time.

10 INPUT CENT

Add this line and RUN AGAIN.

5 PRINT "HOW MANY CENTIMETERS"

Description of Frames for 18 Writing Programs One Type NEW and try this program.





When you are ready, load Lesson Five on the cassette. You must turn over the cassette, Writing Programs One, to Side 2. Refer to General Instructions for Loading the Cassette Tape. Remember to reset the Program Recorder counter to 000.

LESSON FIVE: Frame 18 COMPUTER LOGIC




Frame 19






Frame 21


Frame 20



Frame 22



Frame 23



Frame 24: Summary of Lesson Five

- IF/THEN program statements provide for conditional logic sequencing. If a stipulated condition holds true, the computer performs the instruction present in the THEN command. If the condition proves false, the computer ignores the THEN portion of the statement and goes to the next program line.
- 2. Logical Operators are:
 - = means "equals"


An **IF/THEN** statement comparison between two string variables will only hold true if the strings prove equal, character for character.

- <> means "not equal"
- > means "greater than"
- < means "less than"
- 3. **GOTO** provides for an unconditional logic sequence. The computer moves to the specified line and continues processing.
- 4. Use the BREAK key to end computer execution of an infinite loop.

Frame 25: Practice Session for Lesson Five


Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

READY 5 DIM AS(10) 10 PRINT "PROGRAM TO FIGURE SOCIAL SECURITY TAX" 20 PRINT "HHAT'S YOUR INCOME?" 30 INPUT MOMEY 40 IF MONEY)222900 THEN MONEY=22900 50 PRINT "ARE YOU SELF-EMPLOYED?" 60 INPUT AS 70 IF AS="NO" THEN TAX=MONEY*0.0613 80 IF AS="YES" THEN TAX=MONEY*0.1226 90 PRINT "YOU WILL PAY \$"; 100 PRINT TAX	



Change line 40 in the above program to GOTO 5. Why doesn't this work?


Run the following program and make three intentional mistakes to see how the loop ends.



When you are ready, load Lesson Six on the cassette by typing **CLOAD** and pressing RETURN twice. After the READY message appears on the screen, type **RUN** and press RETURN to start the lesson.

LESSON SIX: LIBRARY FUNCTION

Frame 26



Frame 27

LOG(X) = Logarithm SIN(X) = Sine COS(X) = CosineSGN(X) = Sign-plus or minus


Frame 28: Summary of Lesson Six

- 1. Library functions perform their intended calculation based upon previously established internal programming. Therefore, the use of these functions allows you to "return" a number in the form you need for further computation in a calculation or storage in a variable.
- 2. Common library functions include:
 - INT rounds a number to its next lower whole number.
 - ABS gives you the value of a number without the + or sign.
 - RND used with (0) gives a random number between 0 and 1.
 - SQR gives you the square root of a number.
 - FRE used with (0) tells how much free memory is available.

Frame 29: Practice Session for Lesson Six

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

Here's a program that tells whether a number is odd or even.




Try this program with different inputs. Then BREAK it.

ARE YOU?" *X) THEN PRINT "WHAT KIND OF NAM THEN PRINT "WHO!!?" Then print "Nice Name"


When you are ready, load Lesson Seven on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON SEVEN: Frame 30 FOR/NEXT LOOPS




Program continues until loops are completed.

Frame 31







Frame 33

RE4 10 15	PRINT : PRINT :	SIMPLE THIS P	RES	ERVATI Am Wil	ONS SY L ALLO	STEM"	0
10 18	SEE" PRINT '	WHAT S	EAT	CAN YO	U SELL	NEXT:	
20 30 40 55 60	PRINT F FOR S=1 PRINT	TO 5 ROW"; TO 10 SEAT"; TYPE 1		N THIS	SEAT	I5 50L	
70 80 90	NEXT S	OLD "ALL S	OLD	ошт"			

Frame 34: Summary of Lesson Seven

A FOR/NEXT counting loop repeats a program segment by executing those statements contained within the loop a given number of times.


Set a dummy variable X at 1 and end the loop after a specified number of increments.

In the program above, line statement 50 tells the computer to return to the FOR statement line and process back down to line 50. Each time the computer encounters this program line, X increments by 1 and returns to the beginning of the FOR/NEXT loop until all program lines contained between the FOR/NEXT statements are executed. The "loop" process continues until the desired number of times is reached. At that point, execution of the program advances to the next consecutive numeric line statement.

Frame 35: Practice Session for Lesson Seven


Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

Run the following program.




Change line 10 to get more loops.

The following program generates ten math problems.



Change the program so you get problems with larger numbers. The next program prints a line of dots.



After running the program, add these lines to make a "nested" loop and run it again.

- 15 FOR Y = 1 TO X
- 25 NEXT Y
- 26 PRINT

Then change this line.

10 FOR X=10 TO 1 STEP -1

Add these lines.

- 11 Z=37-X
- 12 FOR A = 1 TO Z
- 13 PRINT " ";
- 14 NEXT A

Change the program to invert the triangle but leave it at the right.

CONGRATULATIONS! GO ON TO THE FINAL QUIZ ON THE CASSETTE.

Take the Final Quiz for Writing Programs One. The program will automatically calculate your scores after you complete the quiz. Load the Final Quiz in the same manner in which you loaded the other lessons. Proceed to the next section of this workbook by loading your cassette, Writing Programs Two, using the procedure outlined in General Instructions for Loading the Cassette Tape.

5

SUMMARY OF LESSONS: WRITING PROGRAMS TWO

Lesson One: Screen Formatting Instructions

Shows method for clearing screen and demonstrates how to position the cursor and print in columns.

Lesson Two: READ/DATA

Shows how to assign values to different variables through the use of READ and DATA statements.

Lesson Three: Arrays

Shows how to set up single-dimension arrays and how to use them in a program.

Lesson Four: PEEK and POKE

Explains computer memory and how to access it directly by means of PEEK and POKE statements.

Lesson Five: ATASCII Code and Instructions

Explains ASCII code as it relates to the ATARI Personal Computer System, and how to use the CHR\$ and ASC functions.

Lesson Six: String Handling

Demonstrates how to examine the contents of string variables and how to use parts of the contents in logic statements.

Lesson Seven: Multiple Statements

Shows how to write lines with more than one statement. Explains logic flow when multiple statement lines are used with IF/THEN statements.

Lesson Eight: Subroutines

Explains the concept of subroutines and demonstrates the use of GOSUB and RETURN.

Final Quiz: Writing Programs Two

A review of the material covered in Writing Programs Two. No voice track is used with this part of the program.

WRITING		CASSETTE RECORDER COUNTER VALUE				
PROGRAMS TWO	LESSON	START LOADING	START AUDIO	END AUDIC		
SIDE 1	1	000				
	2					
Ī	3					
	4					
SIDE 2	5	000				
	6					
	7					
ľ	8					
1	FINAL TEST					

Figure 3 Program Recorder Counter Numbers for Lessons in Writing Programs Two

6

DESCRIPTION OF FRAMES FOR WRITING PROGRAMS TWO

LESSON ONE: SCREEN FORMATTING INSTRUCTIONS

Frame 1: Summary of Lesson One

- 1. **CURSOR**: Wherever the cursor appears on the screen, the computer will accept input and display the character received from the keyboard.
- GRAPHICS 0: Clears the screen of text and sets the background color to blue. The cursor will automatically move to the top and extreme left of the screen, commonly called the "home" position.
- 3. **SEMICOLON**: Use of the semicolon in a PRINT statement keeps the output from moving down to the next line when text and numbers are printed on the screen.

Example: 10 DIM NAME\$(20) 20 NAME\$="JOE" 30 PRINT "MY NAME IS ";NAME\$;"."

MY NAME IS JOE.

4. **COMMA**: Working in a fashion similar to the semicolon, the comma places the printed text or numbers into zones on the screen.

Example: PRINT "ONE","TWO","THREE" PRINT 1,2,3


 ONE
 TWO
 THREE

 1
 2
 3


Frame 2: Practice Session for Lesson One

Note: To clear RAM computer memory, type **NEW** and press **BETURN** before EVERY practice session and between each example program.

The following program illustrates the use of the comma and the semicolon.



Now run this program:



This program illustrates the use of the comma to make columns.

10 PRI 20 PRI 25 PRI	IICS 0 IT "NUMBER IT NUMBER=1 NUMBER=1 ROOT=SORO IT NUMBER, NUMBER		01"

The next program illustrates how text can be strung together with semicolons. To view parts of the program **LIST** as follows:

LIST 10,50

This will list all lines between 10 and 50.


READY	24
5 DIM PLACES(16) 6 DIM PARTS(16)	And the second second
7 DIM LIQUIDS(16)	
10 GRAPHICS 0	
20 PRINT "TYPE IN THE NAME OF A P	LACE
OR THING:"	
30 INPUT PLACES	
40 PRINT "TYPE IN THE NAME OF A B	ODY P
ART:"	
50 INPUT PARTS	
60 PRINT "NAME A LIQUID:" 70 INPUT LIQUIDS 80 PRINT "HERE IS YOUR MADLIB:"	
70 INPUT LIQUIDS	
90 PRINT "JACK AND JILL"	
100 PRINT "WENT UP THE ";PLACES	
110 PRINT "TO FETCH A PAIL OF":LI	OUID S
120 PRINT "JACK FELL DOWN"	
130 PRINT "AND BROKE HIS ";PARTS	
148 PRINT "AND JILL CAME TUMBLING AF	TER!"
150 END	
	1

When you are ready, load Lesson Two on the cassette by typing **CLOAD** and pressing RETURN twice. After the READY message appears on the screen, type **RUN** and press RETURN to start the lesson.


LESSON TWO: READ/DATA

Frame 3

The **READ** and **DATA** statements contained in the following program illustrate the method of execution used by the computer. When a **READ** statement is encountered, the first **DATA** statement is scanned by the computer. The assigned variable receives the initial value contained in the **DATA** statement. This value will remain constant until a new **READ** instruction is encountered.



Frame 4



Frame 5: Practice Session for Lesson Two

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

- 10 READ A
- 20 PRINT A
- 30 GOTO 10
- 40 DATA 5, 6, 7, 8

Run the above program and then add the following line to it.

25 IF A=8 THEN RESTORE

Add the following lines:

- 5 LET B=0
- 26 LET B = B + 1
- 27 IF B=8 THEN STOP

Add the following line.

6 DATA 1, 2, 3, 4


Add the following lines.

10 READ X, Y
 20 PRINT X, Y

And delete 35, 36, and 37.

Description of Frames for 34 Writing Programs Two

Run the following program:



When you are ready, load Lesson Three on the cassette by typing **CLOAD** and pressing RETURN twice. After the READY message appears on the screen, type **RUN** and press RETURN to start the lesson.

LESSON THREE: ARRAYS

Frame 6: Summary of Lesson Three

 Arrays are sets of variables with the same name. Each array variable has the name (in capitals) followed by a number in parentheses. If only one number is assigned, the array is one dimensional. Visualize the elements in the array being placed in one long column. For maximum speed and efficiency of operation, dimension your arrays into rows and columns. The first number within the parentheses indicates the assigned row, and the second number indicates the assigned columm in a two-dimensional array. Carry this concept into n-dimensions by simply adding rows and columns.

Examples of one-dimensional arrays:

A(10), VAR(5) or VAR(X) or ARRAY(NUM)

Examples of two-dimensional arrays:

A(10,50), VAR(5,5) or VAR(X,Y) or ARRAY(ROW, COLUMN)

Arrays must first be set up in ATARI BASIC with a DIM (dimension) statement.

DIM VAR(10)

3. Values can be placed into and removed from array variables with simple **FOR/NEXT** loops.


10 DIM ARRAY(10) 20 FOR X=1 TO 10 30 LET ARRAY(X)=25.2 40 NEXT X 4. The LET instruction in the above program, Statement 30, places a value in the array variable. When **READ/DATA** statements and **INPUT** statements are used to place values into array variables, the computer must use these instructions indirectly. For example,

READ N LET A(X) = N, etc.


Frame 7: Practice Session for Lesson Three

Note: To clear RAM computer memory,type **NEW** and press **RETURN** before every practice session and between each example program.


Run the following program:



When setting up an array it is necessary to store values in each variable in the array, as in the following example. Run the next program, and then check what is in each variable with a **PRINT** instruction, such as **PRINT** A(3).



Add the following lines to the previous program and run it again:



Run this sample program:

JOGGING CALENDER" (SHORTENED TO 7 DAYS)" E(7) 0 7 Many Miles Did You Jog O LES (DAY)=MILES

Run this sample program:

	READY	
	5 GRAPHICS	5 0
	6 DIM FLI	GHŤ (7)
	15 PRINT	THIS IS THE RESERVATION SYST
	EM FOR"	
		FLY-BY-NIGHT AIRWAYS."
		YOU CAN RESERVE FLIGHTS 1-7."
		1 TO 7
	70 LET FL	1 TO 7 IGHT(N)=4
	80 NEXT N	WHAT FLIGHT (1 THRU 7) DO YO
	U WANT?"	WHAT PLIGHT II THEO 73 00 10
	100 INPUT	N
	110 IF FL	IĞHT(N)=0 THEN PRINT "SORRY. Is taken. Try another."
	120 TE EL	EGHT(N) <>0 THEN FLIGHT(N) =FLI
	GHT (N)-1	
	160 IF FL	EGHT(N)<>0 THEN PRINT "ISSUE R FLIGHT ";N 90
	170 COTO	R FLIGHI ";N
L D	3010	
	and a second second	

When you are ready, load Lesson Four on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON FOUR: PEEK and POKE

Frame 8: Computer Memory

The computer's raw memory is like a set of post office boxes, where each box contains just one number ranging from 0 to 255. Each box or location is given an address.

An 8K computer has about 8000 different memory locations that can be used for program storage.

Each number in memory can serve to represent a number, a letter, or a computer instruction. For example, the number 76 could stand for the letter L, or it could act like a **GOTO** instruction for the computer's machine language. What the number represents exactly depends on where it is in memory.

Frame 9: POKE

POKE 54018, 52		Memory address is 54018 Instruction to turn on Program Recorder is 52.
POKE 54018, 60	8	Instruction to turn off Program Recorder is 60.

Frame 10: PEEK


PRINT PEEK (800) prints the number stored in memory location 800.

X = PEEK(800) places the number stored in memory location 800 into the variable X.

Frame 11: Practice Session for Lesson Four

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

Try this program to see the numbers stored in different memory locations:



Use **POKE** instructions with caution. No damage results to the computer physically, but you can crash your program! Try this **POKE** to see a small example of what we mean:

POKE 755,4

To correct the "damage," type in POKE 755,2.

Memory location 20 is used by the computer to count the number of frames the computer puts on your television set. The number in 20 starts at 0 and 1 is added every 1/60th of a second. When the number hits 255, the contents start again at 0.

You can POKE 20 and put the number 0 in it to start. It will then count 1/60ths of a second, as in the following program:



The next program turns on your Program Recorder and allows it to run for 4 seconds. The Program Recorder turns off automatically.

When you are ready, load Lesson Five on the cassette. You must turn over the cassette, Writing Programs Two, to Side 2. Refer to General Instructions for Loading the Cassette Tape. Remember to reset the Program Recorder counter to 000.

LESSON FIVE: ATASCII CODE AND **INSTRUCTIONS**

(This is a sample of the 255 possible characters of ATASCII)

Frame 12: Some ATASCII Characters and Their Code Numbers

Frame 13: Interesting ATASCII Characters

PRINT CHR\$(125)	Clears television screen
PRINT CHR\$(253)	Produces a buzzing sound
PRINT CHR\$(28)	Moves cursor up one line (without erasing anything)
PRINT CHR\$(29)	Moves cursor down one line
PRINT CHR\$(30)	Moves cursor over one space to the left
PRINT CHR\$(31)	Moves cursor over one space to the right

Frame 14: Summary of ASC and CHR\$

CHR\$(N) will produce the character of the ATASCII number.

ASC(L\$) will produce the ATASCII number of the character stored in L\$.


PRINT CHR\$(65) will print the letter A from the ATASCII code number 65.

PRINT ASC("A") will print the ATASCII number 65.


Frame 15: Practice Session for Lesson Five

Note: To clear RAM computer memory,type **NEW** and press **RETURN** before every practice session and between each example program.

The following program will print the whole range of ATASCII characters. Note what happens when CHR\$(125) is printed.




Add the following lines to keep the screen from being erased.




This program will show you the ATASCII code for certain letters and symbols. (Don't use any "invisible" characters.)

S(1) E IN CHARACTER OR SYMBOL' ATASCII CODE FOR ";LETTERS

Press the BREAK key to end program execution. Add this line to the above program and run it again.



Run this line and see what happens. Then try your own program that will print characters on different parts of the television screen.



When you are ready, load Lesson Six on the cassette by typing **CLOAD** and pressing RETURN twice. After the READY message appears on the screen, type **RUN** and press RETURN to start the lesson.

Frame 16

LESSON SIX:

HANDLING

STRING

The following instruction will tell the computer to look at the string stored in WORD\$ starting with the fifth character:

WORD\$(5)

We can print or store the result in another string variable:

PRINT WORD\$(5) PART\$ = WORD\$(5)

Any number can be used in the parentheses just so long as it does not exceed the length of the string stored in the variable.

Example:

STR\$="A SHORT PHRASE" P\$=STR\$(8) PRINT P\$ PHRASE

Frame 17

The following statement will tell the computer to look at the string stored in WORD\$ between two numbers:


WORD\$(5,8)

PRINT WORD\$(5,8) will now print the string from the fifth to the eighth character.

Example: STR\$="A SHORT PHRASE" P\$= STR\$(3,7) PRINT P\$ SHORT

Frame 18

The following program demonstrates how to get one character from a string that has been input into a string variable. In this case the program looks at the first character only.



Frame 19: Practice Session for Lesson Six

Note: To clear RAM computer memory,type NEW and press RETURN before every practice session and between each example program.

Enter the following instructions as direct commands:


DIM WORD\$(40)

LET WORD\$="A SHORT PHRASE"


Now experiment with printing out pieces of the words in WORD\$ by using the following kinds of instructions:

PRINT WORD\$(3) or PRINT WORD\$(5,6) etc.

After trying this a few times, run the following program:



Now add the following lines. (Watch the quotation marks and the semicolons!)



Try this program:

тs

The next program is an analysis program. It looks at a sentence for specific words:

NCE5(40) (SENTENCES) -2 N+2)="THE" THEN PRIN (N,N+2)="THE" THEN PRIN

When you are ready, load Lesson Seven on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON SEVEN: MULTIPLE STATEMENTS

Frame 20

Separate statements can be placed on the same line in a BASIC program if they are separated with a colon (:).

10 GRAPHICS 0 20 PRINT 30 PRINT "THIS IS A VERY SHORT PROGRAM" 40 END

The above program can fit all on one line-

10 GRAPHICS 0: PRINT : PRINT "THIS IS A VERY SHORT PROGRAM": END

Frame 21


The **IF/THEN** condition determines whether statements that follow on the same line will be executed.

10 INPUT A 20 IF A=0 THEN PRINT "TRY AGAIN": GOTO 10 30 PRINT "THAT'S ALL": END

In the above program, the computer will reach the GOTO 10 statement only when A=0. If A <>0, then the computer ignores everything after the **IF/THEN** statement on the same line.

Frame 22: REM (or Remark) Statement

The **REM** statement is a label only. The computer will ignore it. Here the **REM** statement has been added to the program used previously:



The computer will also ignore any statement that follows a **REM** statement on the same line.

10 REM THE NEXT STATEMENT WILL BE IGNORED: GRAPHICS 0

Be very careful with the following in multistatement lines:

REM DATA IF/THEN GOTO

It is safest to have each **DATA** statement on its own line with no other statements.

Frame 23: Practice Session for Lesson Seven

Note: To clear RAM computer memory, type **NEW** and press **RETURN** before EVERY practice session and between each example program.

The following program appeared in an earlier lesson. We have added line 110 to the program so that you can see how much memory the program used. Run the program, and check how much memory you have left.

NUMBER=1 TO 10 SQUARE=NUMBER*NUMBER ROOT=SQR(NUMBER) T NUMBER,SQUARE,ROOT NUMBER 0 PRINT FRE(0);" MEMORY UNITS."

Now rewrite the above program using multiple statement lines, and see how much memory space the new version occupies.

Rewrite the program below using multiple statement lines. See if you can get rid of two of the **IF/THEN** statements.

D 'THE'." ITENCES(N,N+2)="THE" THEN PRIN NTENCES(N) ITENCES(N,N+2)="THE" THEN END


When you are ready, load Lesson Eight on the cassette by typing **CLOAD** and pressing **RETURN** twice. After the READY message appears on the screen, type **RUN** and press **RETURN** to start the lesson.

LESSON EIGHT: SUBROUTINES

Frame 24: Purpose of a Subroutine


In this program, we use the same routine several times, so we moved it to the end. Now it's called a subroutine.

Description of Frames for 48 Writing Programs Two




Frame 25: GOSUB and RETURN Statements


When the computer reaches the **GOSUB** statement in Line 40, it goes to Line 1000.







Frame 26: Question Example



Frame 27: Practice Session for Lesson Eight

Note: To clear RAM computer memory, type NEW and press RETURN before every practice session and between each example program.

The following program has three subroutines. Run it and see what happens.

READY 10 REM SHORT PROGRAM WITH SUBROUTINES 20 GOSUB 100 30 GOSUB 200 40 GOSUB 300 50 GOSUB 200 60 GOSUB 100 20 GOSUB 100	
70 END 100 PRINT :PRINT ''++++++++'':RETURN 200 PRINT :PRINT '''':RETURN 300 PRINT :PRINT ''*********''':RETURN	

The following frame is another version of the program above. However, the **GOSUB** statements use variables instead of numbers.

READY 10 REM SHORT PROGRAM WITH SUBROUTINES 15 LET CROSS=100:LET DASH=200:LET STAR 300 20 GOSUB CROSS 30 GOSUB DASH 40 GOSUB DASH 50 GOSUB CROSS 70 END 100 PRINT : PRINT "++++++++*****************************	

The following program illustrates many of the points taught in the last two lessons.

READY 18 Rem arithmetic program with subrout RINT :PRINT S YOUR NAME?":INPUT NAM ING":PR PROBLEMS *RND(1)):LET B=INT(10*R B;"=";:INPUT C THEN PRINT"WRONG, GOSUB 1000 Student has do

PRINT :GOTO 75 YOU SCORED '';R;" RI (3*RND (1)) PR IF CHOICE TO IF CHOICE=1 THEN PRINT "YOU'VE GO IT, ";NAME5 16'IF'CHOICE=2 THEN PRINT "EXCELLENT 1050 PRINT 1060 RETURN

CONGRATULATIONS! GO ON TO THE FINAL QUIZ ON THE CASSETTE.

You should be ready now for the Final Quiz for Writing Programs Two. Your score will automatically appear on the screen at the conclusion of the quiz. To load the Final Quiz, use the same procedure you used to load the other lessons.

Frame 28: Program to Use With Final Quiz

THEN A=4:8=8+1



Now that you have successfully completed this course, you have acquired the necessary skills for **AN INVITATION TO PROGRAMMING™ 3**. Course content includes BASIC programming of sound and graphics.

LIMITED 90 DAY WARRANTY ON ATARI[®] PERSONAL COMPUTER PRODUCTS

ATARI, INC. ("ATARI") warrants to the original consumer purchaser that this ATARI Personal Computer Product (not including computer programs) shall be free from any defects in material or workmanship for a period of 90 days from the date of purchase. If any such defect is discovered within the warranty period, ATARI's sole obligation will be to repair or replace, at its election, the Computer Product free of charge on receipt of the unit (charges prepaid, if mailed or shipped) with proof of date of purchase satisfactory to ATARI at any authorized ATARI Service Center. For the location of an authorized ATARI Service Center nearest you, call toll-free:

In California (800) 672-1430 Continental U.S. (800) 538-8547 or write to:

Atari, Inc. Customer Service Department 1340 Bordeaux Drive Sunnyvale, CA 94086

YOU MUST RETURN DEFECTIVE COMPUTER PRODUCTS TO AN AUTHORIZED ATARI SERVICE CENTER FOR IN-WARRANTY REPAIR.

This warranty shall not apply if the Computer Product: (i) has been misused or shows signs of excessive wear, (ii) has been damaged by being used with any products not supplied by ATARI, or (iii) has been damaged by being serviced or modified by anyone other than an authorized ATARI Service Center.

ANY APPLICABLE IMPLIED WARRANTIES, INCLUDING WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, ARE HEREBY LIMITED TO NINETY DAYS FROM THE DATE OF PURCHASE. CONSEQUENTIAL OR INCIDENTAL DAMAGES RESULTING FROM A BREACH OF ANY APPLICABLE EXPRESS OR IMPLIED WARRANTIES ARE HEREBY EXCLUDED. Some states do not allow limitations on how long an implied warranty lasts or do not allow the exclusion or limitation of incidental or consequential damages, so the above limitations or exclusions may not apply to you.

This warranty gives you specific legal rights and you may also have other rights which vary from state to state.

DISCLAIMER OF WARRANTY ON ATARI COMPUTER PROGRAMS

All ATARI computer programs are distributed on an "as is" basis without warranty of any kind. The entire risk as to the quality and performance of such programs is with the purchaser. Should the programs prove defective following their purchase, the purchaser and not the manufacturer, distributor, or retailer assumes the entire cost of all necessary servicing or repair.

ATARI shall have no liability or responsibility to a purchaser, customer, or any other person or entity with respect to any liability, loss, or damage caused directly or indirectly by computer programs sold by ATARI. This disclaimer includes but is not limited to any interruption of service, loss of business or anticipatory profits or consequential damages resulting from the use or operation of such computer programs.

REPAIR SERVICE

If your ATARI Personal Computer Product requires repair other than under warranty, please contact your local authorized ATARI Service Center for repair information.

IMPORTANT: If you ship your ATARI Personal Computer Product, package it securely and ship it, charges prepaid and insured, by parcel post or United Parcel Service.



C015727-06 REV. A